


# Merging Paddocks

## 1. Goal

A fence line has been removed, and two paddocks are now being merged to create a single paddock. We want to keep all historical information from the two paddocks but only see on in our program or App.

## 2. Create New Paddock



	Exclude	Paddock Name	Area (ha)	Arable (ha)	Arable %	Soil Details	Boundary	Arable	Prod System (def.)
1		A1	10	10	100%		[S]		Broadacre
2		A2	74	70	95%		[S]		Broadacre
3		A3	35	35	100%		[S]		Broadacre
4		A4	64	60	94%		[S]		Broadacre
5		A5	80	80	100%		[S]		Broadacre
6		A6	283	280	99%		[S]		Broadacre
7		A7	156	150	96%		[S]		Broadacre
8		A8	220	220	100%		[S]		Broadacre
9		A9	249	240	96%		[S]		Broadacre
10		A10	53	50	94%		[S]		Broadacre
11		A11	64	60	94%		[S]		Broadacre
12		A12	457	450	98%		[S]		Broadacre
13		A13	215	215	100%		[S]		Broadacre
14		A14	56	50	89%		[S]		Broadacre
15		A15	52	50	96%		[S]		Broadacre
16		A16	229	220	96%		[S]		Broadacre
17		A17	60	60	100%		[S]		Broadacre
18		A18	52	50	96%		[S]		Broadacre
19		A19	131	130	99%		[S]		Broadacre
20		A20	205	200	98%		[S]		Broadacre
21		A21	120	120	100%		[S]		Broadacre
22		A22a	66	60	91%		[S]		Broadacre
23		Test1	100						Broadacre
24		Test2	100						Broadacre
25		NEW MERGED PADDOCK							Broadacre

1. Open Adviser program
2. Sync / Open file as required
3. Click Farm tab
4. Click Add New paddock
5. Enter new name of merged paddock

## 3. Merge Maps if applicable

Skip this if maps are not present in file.

1. Click Maps icon
2. Click Boundary icon for any paddock to open Maps Editor
3. Click Tools tab
4. Click on the first paddock to be merged
5. Hold Ctrl, click on second paddock to be merged
6. Click Join Selected Shapes
7. Click Yes on prompt
8. Click Edit tab
9. Click newly joined shape

10. Click Paddocks drop down
11. Double click new paddock name
12. Tick Auto-Area if desired
13. Click Save
14. Click windows X to close

#### 4. Exclude old paddocks from View

Tick the Exclude box beside the void paddocks, and add a Note to the right to record why the paddock was excluded and when. For example “Paddock A17 and A18 merged 200717, now New Merged Paddock”.

#### 5. Sync file if applicable

These changes will need to be sync'd to CornerPost and retrieved to any other devices used where applicable. To complete, please continue.

1. Click File
2. Click Close
3. Click Refresh File List
4. Ensure file status is Ready, if not wait 5 minutes and repeat from step 3
5. Single click file to highlight
6. Click Sync Selected Files with CornerPost
7. Click OK on Manual Sync Complete prompt

You have now successfully merged your paddocks including Maps, and sync'd those changes to CornerPost ready to be retrieved on other devices.

## Good luck, and have fun!

---

**Back Paddock Team.**

**Ph:** 07 3220 2959

**E:** [Support@backpaddock.com.au](mailto:Support@backpaddock.com.au)

**W:** [www.backpaddock.com.au](http://www.backpaddock.com.au)